

## Installing the eBook Librarian Software

**Note:** LINK libraries will need to contact the help desk for installation of software to LINK machines.

1. Verify that your machine meets the system requirements necessary for the eBook Librarian:
  - PC with Windows 95, 98 or 2000
  - 16 MB RAM
  - 10 MB of free disk space
  - An Internet Connection
  - A USB port on your computer
2. Insert the eBook Librarian CD into your CD drive. The installation program will automatically begin.
3. Click the “Cancel” button. We’ll install the software through the Control Panel instead.
4. From your “Start” menu, choose “Setting” and then choose “Control Panel.”
5. Choose “Add/Remove Programs.”
6. The next few steps vary depend on if you are running Windows 2000 or another version of windows.

For Windows 2000:

- a. Choose “Add New Programs.”
- b. Click the “CD or Floppy” button.
- c. You will be instructed to insert the floppy or CD. Just click “Next.”
- d. You will be told that the installation program couldn’t be found. Click the “Browse” button, choose your CD drive, and then choose “r120\_241eBookLibrarian.exe.” (NOTE: In order to see the .exe file, you will need to change the “Files of Type” box to “All Files.”)
- e. Click “Open.”
- f. Click the “Finish” button and the installation will begin.

For Windows 95/98:

- a. Click the “Install” button.
- b. You will be instructed to insert the floppy or CD. Just click “Next.”
- c. You will be told that the installation program couldn’t be found. Click the “Browse” button, browse to your CD drive, and then choose “r120\_241eBookLibrarian.exe.”
- d. Click “Open.”
- e. Click the “Finish” button and the installation will begin.

7. The first installation screen will appear, welcoming you to the setup program. Click the "Continue" button.
8. The setup will unpackage, and another Welcome screen will appear. Click the "Next" button to continue.
9. The license agreement will appear. Click the "Yes" button to continue.
10. The "Choose Destination Location" screen will appear. Accept the default location, unless you have a specific reason not to. Click the "Next" button to continue.
11. You will be asked to select a program folder. Accept the default, and click the "Next" button to continue.
12. You will be given the opportunity to review the settings you have chosen. Click the "Next" button to continue.
13. The software will install, and you will receive a screen telling you that the installation is complete. Click the "Finish" button.

The first time you connect your REB1100 to your computer, you will need to install some drivers for the hardware. Windows should automatically find the new hardware and prompt you for the location of the drivers. The drivers are on the CD with the installation program. Enter the letter of your CD drive in the box when prompted. NOTE: If you are installing the program on a LINK machine, you will need to contact the help desk for installation of the drivers.